A quick guide on how to use Matlab netCDF functions

Prepared by HP Huang (hp.huang@asu.edu), Sept 2009. **Revised March 2015**. Please email HPH for any questions/comments.

A netCDF file contains two parts: A "header" that describes the names, dimensions, etc., of the variables stored in the file, and the main body that contains the real data. To process a netCDF file, we need to first extract the information in the header and determine what portion/segment of the data we want to use. This is usually done by using a set of stand-alone tools. This is, in fact, the more tedious task which we will discuss in Part (A). Once the content of a netCDF file is known, it is rather straightforward to read the data as will be discussed in Part (B).

(A) Inspect the content of a netCDF file

We will use the netCDF data file, **precip.mon.ltm.nc**, as an example to explain how the Matlab functions work. This file, extracted and downloaded from the the NOAA ESRL-PSD web portal (www.esrl.noaa.gov/psd), contains the CMAP gridded data for the long-term mean of monthly precipitation for the global domain. It contains the values of precipitation rate on a regular longitude-latitude grid for the climatological means for January, February, ..., December.

Step 0: Display/check the header of the netCDF file

ncdisp('precip.mon.ltm.nc')

The output is listed in Appendix A.

Remark: The ncdisp command "dumps" out the whole header, which contains the essential information about the variables and their dimensions in the netCDF file. Running ncdisp is equivalent to running "ncdump -c" (see Appendix B) on Linux-based platforms. It is strongly recommended that the information in the header be examined before one uses the data in a netCDF file. In fact, just by carefully inspecting the header, one can skip many steps discussed in Step 2-4 in this section.

Step 1: Open the file

ncid1 = netcdf.open('precip.mon.ltm.nc','NC_NOWRITE')

Remark: This command "opens" a netCDF file named precip.mon.ltm.nc and assigns a file number to it. This file number is the sole output of the function and is put into our variable, ncid1, for later uses. The option 'NC NOWRITE' designates that the file is read-only (that is what we need for now).

Steps 2-4 are often not necessary if one has already obtained the needed information about specific variables by running ncdisp in Step 0.

Step 2: Inspect the number of variables and number of dimensions, etc., in the file

[ndim, nvar, natt, unlim] = netcdf.inq(ncid1)

ndim = 3

```
nvar = 4
natt = 6
unlim = 2
```

Remark: After opening a file and obtaining its "file number", we next inquire what's in the file. The output of the function, netcdf.inq, is a four-element array that contains the number of dimension, number of variable, number of attribute, etc. (Let's focus on the first two elements for now.) From those outputs, we learned that the file, "precip.mon.ltm.nc", contains 4 variables (nvar = 4) and maximum of 3 dimensions (ndim = 3).

```
Step 3: Extract further information for each "dimension"

[dimname, dimlength] = netcdf.inqDim(ncid1, 0)

dimname = lon

dimlength = 144

[dimname, dimlength] = netcdf.inqDim(ncid1, 1)

dimname = lat

dimlength = 72

[dimname, dimlength] = netcdf.inqDim(ncid1, 2)

dimname = time

dimlength = 12
```

Remark: From Step 2, we learned that there can be maximum of three dimensions for any variable stored in 'precip.mon.ltm.nc'. We then call the function, **netcdf.inqDim(ncid, dimid)**, to ask about the detail of each dimension, *one at a time*. Note that the parameter, **dimid**, runs from 0 to 2 instead of 1 to 3 (dimension number zero, *dimid* = 0, corresponds to the 1st dimension; dimension number one, *dimid* = 1, corresponds to the 2nd dimension, and so on). This is because Matlab netCDF utilities adopt the convention of C language, in which the counting of numbers often starts from zero instead of one. Here, we stop at dimension number 2 (or, the 3rd dimension) because from Step 2 we already determined that the maximum number of dimension is 3. From this step, we know that the coordinate for the first dimension is stored in an array called "lon" with 144 elements, the 2nd dimension is "lat" with 72 elements, and the 3rd dimension is "time" with 12 elements.

Step 4: Extract further information for each variable

```
[varname, xtype, dimid, natt] = netcdf.inqVar(ncid1, 0)

varname = lat
```

```
xtype = 5
dimid = 1
natt = 3
```

Remark: In this example, we first extract the name, dimension, etc., of the *first* variable. Again, for this function, netcdf.inqVar(ncid1, varid), the parameter "varid" starts from 0 instead of 1. This is a convention adopted from C language; See remarks for Step 3. The outcome tells us that the 1st variable is named "lat". It is of type "5" which translates to "float" or "real". (The Matlab documentation provided by mathworks.com does not have the detail on this point, but the definition of *xtype* is available from the documentation for the C interface for netCDF; See p. 41 of that documentation. Some commonly encountered types are 2 = character, 3 = short integer, 4 = integer, 5 = real, and 6 = double.) Note that if one simply reads the header obtained by running ncdisp in Step 0, one would immediately see that the "lat" variable is of "real" or "float" type.

The "dimid = 1" in the output tells us that the variable "lat" is a one-dimensional array (because dimid is a single number, not an array) and the coordinate in that dimension is defined by "dimension number 1". Recall that in Step 3 the comamnd, [dimname, dimlength] = netcdf.inqDim(ncid1, 1), returned dimname = lat, dimlength = 72. Therefore, the variable "lat" is an array with 72 elements, and the coordinate for these 72 elements are defined by the dimension, "lat", which itself has 72 elements. (Here, "lat" is both a variable and a dimension or coordinate. If this sounds confusing, keep reading and it will clear later.) Let's not worry about the 4th parameter ("attribution") for now.

[varname, xtype, dimid, natt] = netcdf.inqVar(ncid1, 1)

```
varname = lon
xtype = 5
dimid = 0
natt = 3
```

Remark: We find that the second variable is called "lon". It is of "real" type. It is a one-dimensional array with its coordinate defined by "dimension number zero", i.e., the 1st dimension or "lon", with 144 elements. Again, "lon" is both a "variable" and a "dimension" (or coordinate).

```
[varname, xtype, dimid, natt] = netcdf.inqVar(ncid1, 2)
```

```
varname = time
xtype = 6
dimid = 2
```

```
natt = 6
```

Remark: The third variable is called "time". It is of "double" type (xtype = 6). It is a one-dimensional array with its coordinate defined by "dimension number 2", i.e., the 3rd dimension or "time", with 12 elements. Again, "time" is both a "variable" and a "dimension" (or coordinate). (This is very common of a netCDF file.)

[varname, xtype, dimid, natt] = netcdf.inqVar(ncid1, 3)

```
varname = precip
xtype = 5
dimid = 0, 1, 2
natt = 14
```

Remark: We now obtain the information of the 4th and final variable. (We know there are only 4 variables in this file because nvar = 4 in Step 2.) It is named "precip". It is of "real" type. It is a three-dimensional variable, because dimid = [0, 1, 2], an array with three elements. Moreover, the 1st dimension corresponds to "dimension number zero" given by Step 3, the 2nd dimension corresponds to "dimension number 1", and the third dimension corresponds to "dimension number 2". Therefore, the variable "precip" has the dimension of (144, 72, 12), with total of 144x72x12 elements of real numbers. The coordinates for the 1st, 2nd, and 3rd dimensions are defined by lon(144), lat(72), and time(12).

Summary

From the above, we learned that there are four variables in the netCDF file, "lon", "lat", "time", and "precip". The first three are there only to provide the coordinate (or "metadata") for the 4th variable, which contains the real data that we want to use. Symbolically, the 4th variable is

precip:
$$P(\lambda(i), \phi(j), t(k))$$
, $i = 1-144, j = 1-72$, and $k = 1-12$,

and the first three are

$$lat: \Phi(j)$$
, $j = 1-72$ $lon: \lambda(i)$, $i = 1-144$ $time: t(k)$, $k = 1-12$

The arrangement of the block of data for "precip" is illustrated in Fig. 1.





Fig. 1

Here, we use the "normal" convention with each of the indices, i, j, and k, starting from 1, whereas the Matlab netCDF functions adopt C convention such that the counting starts from zero. Figure 2 is a slightly modified diagram that illustrates the actual numbers that we should use to extract the data using the Matlab functions.



(B) Read a variable from the netCDF file

From Part (A), we now know the content of the netCDF file. We will next use some examples to illustrate how to read a selected variable, or a "subsection" of a variable, from the file. This is generally a very straightforward task and only involve calling the function, **netcdf.getVar**, in a one-line command. (Read the documentation for that function at mathworks.com. It is useful.)

Example 1: Read the content of the variable "lat" (this is the latitude for the precipitation data)

```
lat1 = netcdf.getVar(ncid1,0,0,72)

Result:

88.7500
86.2500
83.7500
81.2500
78.7500
76.2500
...
...
-81.2500
```

-83.7500 -86.2500 -88.7500


ncid1 = netcdf.open('precip.mon.ltm.nc','NC NOWRITE');

Remark: The first line of command opens the file and assigns it a file number, which is returned to ncid1. In the second line, lat1 = netcdf.getVar(ncid1, varid, start, count), we choose

- ncid1 as the outcome from first line of code, so we know that the file we will be using is "precip.mon.ltm.nc"
- varid = 0, which means we read variable number zero, or the *1st variable*, which is "lat", a real array with 72 elements see Step 4 in Part A. As always, remember that Matlab netCDF functions adopt the convention of C language: The counting starts from zero instead of one. See further remark at bottom of Step 3 in Part A.
- start = 0, which means we read the segment of the variable starting from its 1st element. (Again, remember that counting starts from zero.)
- **count** = **72**, which means we read total of 72 elements, starting from the 1st element (as defined by **start** = **0**). In other words, we read the array, [lat(1), lat(2), lat(3), ..., lat(71), lat(72)], and put it into our own variable, lat1, in the left hand side. As Matlab dumps the content of lat1, we see that the contents of "lat" in the netCDF file are [88.75, 86.25, 83.75, ..., -86.25, -88.75]. These are the latitude (from 88.75°N to 88.75°S) for the precipitation data.

Example 2: Read the full 144×72 global precipitation field for time = 1 (i.e., January climatology), then make a contour plot of it

Result:



Remarks: Only the first 4 lines of the code are related to reading the netCDF file. The rest are commands for post-processing and plotting the data. In the second line,


PrecJanuary = netcdf.getVar(ncid1, varid, start, count) ,

we choose **ncid1 from the outcome of the first line of code**, so we know that the file we are using is "precip.mon.ltm.nc". In addition, **varid** = **3**, which means we read the 4th variable, "precip"; **start** = [**0 0**], which indicates that we read the 1st, 2nd, and 3rd dimension from i = 0, j = 0, and k = 0 as illustrated in Fig.2; **count** = [**144 72 1**], which indicates that we actually read i = 0-143 (the total count of grid point is 144), j = 0-71 (total count is 72), and k = 0-0 (total count is 1) in Fig. 2 (which correspond to i = 1-144, j = 1-72, k = 1-1 in Fig. 1). Essentially, we just cut a 144 x 72 slice of the data with k = 1.

Example 3: Read the full 144×72 global precipitation field for time = 1 (i.e., January climatology), then make a color+contour plot of it

```
ncid1 = netcdf.open('precip.mon.ltm.nc','NC NOWRITE');
precJanuary = netcdf.getVar(ncid1,3,[0 0 0],[144 72 1],'double');
lon1 = netcdf.getVar(ncid1,1,0,144);
lat1 = netcdf.getVar(ncid1,0,0,72);
for p = 1:144
for q = 1:72
 if abs(precJanuary(p,q)) > 99
   precJanuary(p,q) = 0;
 end
 map1(q,p) = precJanuary(p,q);
end
end
pcolor(lon1,lat1,map1)
shading interp
colorbar
hold on
contour(lon1,lat1,map1,'k-')
```

Result:



Remark: This example is almost identical to Example 2, but note that in the second line,

PrecJanuary = netcdf.getVar(ncid1, varid, start, count, output_type),

we have an extra parameter, **output_type = 'double'**. This helps convert the outcome (which is put into our variable, PrecJanuary) from "real" to "double" type. This is needed in this example, because the function, pcolor (for making a color map) requires that its input be of "double" type. [Typically, for a 32-bit machine, variables of "real" and "double" types contain 4 bytes (or 32 bits) and 8 bytes (or 64 bits), respectively. This detail is not critical.] Without the extra parameter for the conversion, as is the case with Example 2, Matlab would return the values of the variable in its original type, which is "real". (We know it from Step 4 in Part (A) that xtype = 5 for this variable.)

Appendix A. The header of a netCDF file as the output from the example in Step 0

Executing the command, ncdisp('precip.mon.ltm.nc'), would produce the following detailed output which is the header of the netCDF file, precip.mon.ltm.nc.

```
Source:
```

m:\small_project\precip.mon.ltm.nc

Format:

classic

Global Attributes:

Conventions = 'COARDS'

title = 'CPC Merged Analysis of Precipitation (excludes NCEP Reanalysis)'

```
= 'created 12/98 by CASData version v207
      history
      platform
                 = 'Analyses'
      source
                 = 'ftp ftp.cpc.ncep.noaa.gov precip/cmap/monthly'
      documentation = 'http://www.cdc.noaa.gov/cdc/data.cmap.html'
Dimensions:
      lon = 144
      lat = 72
      time = 12 (UNLIMITED)
Variables:
  1at
      Size:
               72x1
      Dimensions: lat
      Datatype: single
      Attributes:
                      = 'degrees north'
             units
             actual range = [8.88e+01 - 8.88e+01]
             long name = 'Latitude'
  lon
      Size:
               144x1
      Dimensions: lon
      Datatype: single
      Attributes:
             units
                      = 'degrees east'
             long name = 'Longitude'
             actual range = [1.25e+00 \ 3.59e+02]
  time
      Size:
               12x1
      Dimensions: time
      Datatype: double
      Attributes:
                      = 'hours since 1-1-1 00:00:0.0'
             units
             long name = 'Time'
                      = '0000-01-00 00:00:00'
             delta t
             actual range = [0.00e+00 8.02e+03]
             avg period = '0000-01-00\ 00:00:00'
             ltm range = [1.73e+07 1.75e+07]
  precip
      Size:
               144x72x12
      Dimensions: lon,lat,time
      Datatype: single
      Attributes:
             long name
                                = 'Average Monthly Rate of Precipitation'
             valid range
                                = [0.00e+005.00e+01]
                             = 'mm/day'
             units
                               = 0
             add offset
             scale factor
                               = 1
             actual range
                                = [0.00e+003.41e+01]
```

```
missing_value = -9.97e+36

precision = 3.28e+04

least_significant_digit = 2

var_desc = 'Precipitation'

dataset = 'CPC Merged Analysis of Precipitation Standard'

level_desc = 'Surface'

statistic = 'Mean'

parent_stat = 'Mean'
```

Appendix B: Obtaining the header using Linux-based utilities

The header of a netCDF file can also be extracted by using Linux-based utilities. The most commonly used tool is "ncdump". The Linux equivalent of running "ncdisp('precip.mon.ltm.nc') is

ncdump -c precip.mon.ltm.nc

Note that the "-c" option is essential. With it, the command only dumps the header. Without it, the command will dump all data in the netCDF file.

Result:

```
netcdf precip.mon.ltm {
dimensions:
       lon = 144;
       lat = 72;
       time = UNLIMITED; // (12 currently)
variables:
       float lat(lat);
               lat:units = "degrees north";
               lat:actual range = 88.75f, -88.75f;
               lat:long name = "Latitude";
       float lon(lon);
               lon:units = "degrees east";
               lon:long name = "Longitude";
               lon:actual range = 1.25f, 358.75f;
       double time(time);
               time:units = "hours since 1-1-1 00:00:0.0";
               time:long name = "Time";
               time:delta t = "0000-01-00\ 00:00:00";
               time:actual range = 0., 8016.;
               time:avg period = "0000-01-00 00:00:00";
               time:ltm range = 17338824., 17530944.;
       float precip(time, lat, lon);
               precip:long name = "Average Monthly Rate of Precipitation";
               precip:valid range = 0.f, 50.f;
               precip:units = "mm/day";
               precip: add offset = 0.f;
               precip:scale factor = 1.f;
               precip: actual range = 0.f, 34.05118f;
```

```
precip:missing value = -9.96921e+36f;
                precip:precision = 32767s;
                precip:least significant digit = 2s;
                precip:var desc = "Precipitation" ;
                precip:dataset = "CPC Merged Analysis of Precipitation Standard";
                precip:level desc = "Surface";
                precip:statistic = "Mean";
                precip:parent stat = "Mean";
// global attributes:
                :Conventions = "COARDS" ;
                :title = "CPC Merged Analysis of Precipitation (excludes NCEP Reanalysis)";
                :history = "created 12/98 by CASData version v207\n",
                :platform = "Analyses";
                :source = "ftp ftp.cpc.ncep.noaa.gov precip/cmap/monthly";
                :documentation = "http://www.cdc.noaa.gov/cdc/data.cmap.html";
data:
lat = 88.75, 86.25, 83.75, 81.25, 78.75, 76.25, 73.75, 71.25, 68.75, 66.25,
  63.75, 61.25, 58.75, 56.25, 53.75, 51.25, 48.75, 46.25, 43.75, 41.25,
  38.75, 36.25, 33.75, 31.25, 28.75, 26.25, 23.75, 21.25, 18.75, 16.25,
  13.75, 11.25, 8.75, 6.25, 3.75, 1.25, -1.25, -3.75, -6.25, -8.75, -11.25,
  -13.75, -16.25, -18.75, -21.25, -23.75, -26.25, -28.75, -31.25, -33.75,
  -36.25, -38.75, -41.25, -43.75, -46.25, -48.75, -51.25, -53.75, -56.25,
  -58.75, -61.25, -63.75, -66.25, -68.75, -71.25, -73.75, -76.25, -78.75,
  -81.25, -83.75, -86.25, -88.75;
lon = 1.25, 3.75, 6.25, 8.75, 11.25, 13.75, 16.25, 18.75, 21.25, 23.75,
  26.25, 28.75, 31.25, 33.75, 36.25, 38.75, 41.25, 43.75, 46.25, 48.75,
  51.25, 53.75, 56.25, 58.75, 61.25, 63.75, 66.25, 68.75, 71.25, 73.75,
  76.25, 78.75, 81.25, 83.75, 86.25, 88.75, 91.25, 93.75, 96.25, 98.75,
  101.25, 103.75, 106.25, 108.75, 111.25, 113.75, 116.25, 118.75, 121.25,
  123.75, 126.25, 128.75, 131.25, 133.75, 136.25, 138.75, 141.25, 143.75,
  146.25, 148.75, 151.25, 153.75, 156.25, 158.75, 161.25, 163.75, 166.25,
  168.75, 171.25, 173.75, 176.25, 178.75, 181.25, 183.75, 186.25, 188.75,
  191.25, 193.75, 196.25, 198.75, 201.25, 203.75, 206.25, 208.75, 211.25,
  213.75, 216.25, 218.75, 221.25, 223.75, 226.25, 228.75, 231.25, 233.75,
  236.25, 238.75, 241.25, 243.75, 246.25, 248.75, 251.25, 253.75, 256.25,
  258.75, 261.25, 263.75, 266.25, 268.75, 271.25, 273.75, 276.25, 278.75,
  281.25, 283.75, 286.25, 288.75, 291.25, 293.75, 296.25, 298.75, 301.25,
  303.75, 306.25, 308.75, 311.25, 313.75, 316.25, 318.75, 321.25, 323.75,
  326.25, 328.75, 331.25, 333.75, 336.25, 338.75, 341.25, 343.75, 346.25,
  348.75, 351.25, 353.75, 356.25, 358.75;
time = 0, 744, 1416, 2160, 2880, 3624, 4344, 5088, 5832, 6552, 7296, 8016;
```

Quick exercise: Based on the CMAP data set, what are the climatological values of the precipitation rate for January, February, ..., December at the grid point that is closest to (1) Phoenix, AZ, and (2) Seattle, WA? Make a plot of the results.